



Help Documentation


How to Configure the Reservation System's User Interface Design

Setup – Website Definitions – UI Design

Use this screen to easily customize the user interface components of the Reservation System.

The following screen components can be customized according to your preferences:

- **General** features of the Reservation System
- **Header** section of the Reservation System
- **Footer** section of the Reservation System

Click  after updating any option on this screen.

●General

» Default login page language

From the drop-down list, select the **default language** in which the Travel Booster login page will be displayed to all users.

↗ For a **B2E/B2B/B2S** user: after logging in, the language will be determined by the specific language definition for the user. Before performing the initial login, the login page for all users will be displayed in the default language.

↗ For a **B2C** user: this is the language in which Travel Booster will be displayed.



» Home page

From the drop-down list, select the **default Travel Booster home page** that will be displayed when accessing the system.


- Select **Default** to direct to the B2C site and allow access to all login types.
- Select **Customer** to direct to the B2C site and also allow B2E login.
- Select **Agent** to direct to the B2B site and also allow B2E login.
- Select **Employee** to direct to the B2E site only.
- Select **Supplier** to direct to the B2S site and also allow B2E login.




» **Site color theme**

Use this option to define the color theme of the Reservation System's Website.

1. Click **Select Style** to select a site color theme.

2. Select one of the following themes and then click  .





» Document logo

Use this option to define the logo that will be displayed on all documents issued from the Reservation System.

1. Click .
2. Select the image.

Note that maximum image size is 277 pixels wide by 72 pixels high.
Image must be stored locally.
Maximum file size is 7.8 KB.

3. Click .

↻ If required, click to delete an existing logo.

● Header

» Logo image and icons

Select this option to define a logo that will be displayed in the header section of the Reservation System. The logo will be displayed on the left side of the screen. The standard Travel Booster service icons will be displayed to the right of the logo.

↻ If this option is selected and an image is not uploaded, the default Travel Booster logo will be displayed.

1. Click .
2. Select the image.

Note that maximum image size is 277 pixels wide by 77 pixels high.

3. Click .

↻ If required, click to delete an existing logo.



» Create header





Select this option to create a header that will be displayed across the entire width of the screen. The service names (without their respective icons) will be displayed below the header.

» To upload an existing file

Note that in this option, **only the following file types** can be uploaded:

- HTML
- an archived directory (with extension .zip) containing both HTML and associated files (image, flash, etc.). Ensure that all associated files are on the same level (not in sub-directories) and that all URLs in the HTML source are relative.

The maximum header size is 966 pixels wide by 77 pixels high.

1. Click .
2. Click .
3. Select the file or archived directory.
4. Click .
5. If required, click  to edit the uploaded file/s.

Refer to the **FCKeditor User's Guide** at

http://docs.fckeditor.net/FCKeditor_2.x/Users_Guide for instructions on how to use the text editor's functions.

-  If required, click  to delete an existing header.



» **To create a new header**

Note that maximum header size is 966 pixels wide by 77 pixels high.

1. Click  .

2. Create the header using the text editor.

Refer to the **FCKeditor User's Guide** at

http://docs.fckeditor.net/FCKeditor_2.x/Users_Guide for instructions on how to use the text editor's functions.

3. Click  .

↗ If required, click  to delete an existing header.



● Footer

» Create footer





Select this option to create a footer that will be displayed across the entire width of the screen.

» To upload an existing file

Note that in this option, **only the following file types** can be uploaded:

- HTML
- an archived directory (with extension .zip) containing both HTML and associated files (image, flash, etc.) Ensure that all associated files are on the same level (not in sub-directories) and that all URLs in the HTML source are relative.

The maximum footer size is 972 pixels wide.

1. Click .
2. Click .
3. Select the file or archived directory.
4. Click .
5. If required, click  to edit the uploaded file/s.

Refer to the **FCKeditor User's Guide** at

http://docs.fckeditor.net/FCKeditor_2.x/Users_Guide for instructions on how to use the text editor's functions.

- ↗ If required, click  to delete an existing footer.



» To create a new footer

Note that maximum footer size is 972 pixels wide.

1. Click .

2. Create the footer using the text editor.

Refer to the **FCKeditor User's Guide** at

http://docs.fckeditor.net/FCKeditor_2.x/Users_Guide for instructions on how to use the text editor's functions.

3. Click .

 If required, click  to delete an existing footer.

» Standard site footer

Select this option to define the elements of the standard Travel Booster site footer.

Selecting this option will activate the remaining options in the **Footer** expander.

» Activate home link

Select this option to display the **Home** link in the footer section. After selecting the option, enter the URL of the Website to which the user will be directed when clicking this link.

» Activate main menu link

Select this option to display the **Main Menu** link in the footer section. Clicking this link will direct the user to the query screen for the default service.



» Links

Use this section to define additional links (a maximum of 10) to be displayed in the footer section.

1. In the **Name** field, enter the text to be displayed when hovering over the image representing the link.

Select the box before the **Name** field to activate/deactivate this link.

Name ?

2. Click the triangle by **Picture Not Uploaded** and select **Browse**.



3. Click .
4. Select the image.
5. Click .



 If required, select to delete an existing image.


6. In the **URL** field, enter the URL of the Website to which the user will be directed when clicking this link.


To display the Website in a new window, include the **http:// prefix**.

To display a new Website in the same window, omit the **http:// prefix**. The new URL will be automatically appended to the URL of the currently displayed page.






Use the triangles at the beginning of each link row   to designate the order in which the links will be displayed.

Click  to add an additional link row to the screen.

If required, click  to delete the entire link.

➡ On-Screen Buttons

 Save	Save changes made to Website definition/s on this screen
Configuration	Create, delete, or export Website definitions in a multi-configuration environment
 Exit	Exit to Setup menus
 Help	Open the relevant Help topic